



## INSTALLATION PROCESS

- Unzip files from the zip archive to MetaTrader4 folders. You need to put FXOxygen.ex4 file to Experts folder, and O2.dll file to Libraries folder. You can find these folders through your MetaTrader4 terminal File -> Open Data Folder -> MQL4.
- Reboot MetaTrader4.
- Find FXOxygen in the Navigator window and move it to a EUR/USD or USD/JPY chart.
- Allow DLL imports and live trading in Common options and set Inputs parameters.
- Check if you did everything right.



## REQUIREMENTS

FXOxygen works on EUR/USD and USD/JPY currency pairs only. There are two modes: Secure - for reliable trading, and Boost - for highly profitable trading. Required deposits for each system are:

EUR/USD		
Secure	Boost_1	Boost_2
>\$700	>\$65	>\$55
lot 0.01	lot 0.01	lot 0.01
USD/JPY		
Secure	Boost_1	Boost_2
>\$430	>\$61	>\$72
lot 0.01	lot 0.01	lot 0.01

## RECOMMENDED SETTINGS

Time Frame of the EA is M30. We recommend to use Secure mode (Secure\_System) for each pair with 35% risk. Default Inputs settings of FXOxygen are the recommended.

Boost mode was designed for a highly profitable short-term trading. We do not recommend Boost mode for a stable and reliable trading.

*For Update and Ex4.Unlock Questions..*

*Please contact email:*

*Cs.FXTools@gmail.com*

NO share/reselling.  
if we found out, we will banned your account and your IP without notice.  
You will not get any updates of any item you buy.


## INPUTS OPTIONS

<b>Auto_Lot</b>	Percentage of your deposit, which FXOxygen will work with. The EA sets lot based on this parameter.
<b>Secure_System</b>	Mode for a reliable long-term trading.
<b>Boost1_System</b> <b>Boost2_System</b>	Modes for a highly profitable short-term trading. They have a small difference in TP, SL and time of opening trades.
<b>Secure_Lot</b> <b>Boost1_Lot</b> <b>Boost2_Lot</b>	In case "AutoLot" is equal "0" you can set the desired lot manually there.
<b>Auto_GMTOffset</b>	The EA detects GMT of your broker automatically.
<b>Manual_GMTOffset</b>	In case "Auto_GMTOffset" is equal "false" you can set the desired GMT manually there.
<b>Slippage</b>	You can set the desired slippage manually there. Change this parameter only in case of conscious necessity.
<b>MiniLot_Account</b>	Enable this parameter only in case of using account with mini or micro lot. You should not enable it for a standard and cent accounts with normal lot.

## FAQ

- I installed FXOxygen on my PC/VPS, but I cannot find the EA in Navigator window.

Make sure that you opened the main MQL4 MetaTrader4 folder and copied FXOxygen.ex4 file to Experts folder and O2.dll file to Libraries folder.



For Update and Ex4.Unlock Questions..

Please contact email:

Cs.FXTools@gmail.com

NO share/reselling.  
if we found out, we will banned your account and your IP without notice.  
You will not get any updates of any item you buy.

- MetaTrader4 shows an error "Cannot call 'O2.dll', 'O2.dll' is not loaded".

Check if you allowed DLL imports in Common options of the EA. If you did so, make sure that O2.dll file is in the Libraries folder. Because of our security lock some antivirus programs can detect dll file as a virus and delete it. In that case you need to reinstall FXOxygen and add O2.dll file to exceptions of your antivirus program.

- I installed the EA properly, but it does not seem to trade.

Make sure that you allowed live trading and that the "AutoTrading" button of MetaTrader4 is enabled.

The EA should trade 24/5. It opens a first trade within the next 24 hours after starting. So maybe you just need to wait for a while.

**IF YOU DID NOT FIND THE ANSWER ON YOUR QUESTION IN OUR FAQ CONTACT US BY E-MAIL:  
SUPPORT@FXOXYGEN.COM**

*For Update and Ex4.Unlock Questions..*

*Please contact email:*

*Cs.FXTools@gmail.com*

NO share/reselling.  
if we found out, we will banned your account and your IP without notice.  
You will not get any updates of any item you buy.